



شرکت پرداخت الکترونیک سامان

# راهنمای استفاده از درگاه پرداخت اینترنتی

راهنمای اتصال به neo-pg

مستند فنی

آخرین بروزرسانی: دی ۱۴۰۲

## سابقه بازنگری

اقدام کننده	شرح	نگارش	تاریخ

## نشر

سمت	مرجع	تاریخ	امضا
تهیه کننده	واحد نرم افزار	۱۴۰۲/۱۰/۱۶	

## ۱. پیش نیاز اتصال به درگاه neo-pg

پیش از استفاده از درگاه neo-pg می بایست امکان اتصال به این درگاه را برای ترمینال پذیرنده فعال گردد. جهت فعال نمودن این امکان می بایست با واحد کسب و کار نوین پرداخت الکترونیک سامان هماهنگی لازم انجام پذیرد.

## ۲. تغییرات پیاده سازی نسبت به IPG عمومی:

پس از فعال نمودن امکان neo-pg ترمینال، در header پاسخ سرویس دریافت توکن در فیلد X-IPG-Url آدرس اتصال به درگاه برای پذیرنده ارسال می شود. که پذیرنده از این پس توکن را به این آدرس می بایست ارسال کند.

نکته: فیلدهای دریافتی و ارسالی بین سایت پذیرنده و درگاه پرداخت به نسبت درگاه پرداخت قبلی هیچ گونه تغییری نداشته و تنها تغییر به نسبت درگاه قبلی آدرس پایه می باشد که می بایست از فیلد X-IPG-Url خوانده شود.

## ۳. نمونه درخواست توکن

```
{
  "action": "token",
  "TerminalId": "0000",
  "RedirectUrl": "http://my-company.com/ipg-receipt",
  "ResNum": "12345",
  "Amount": "12000",
  "CellNumber": "9120000000"
}
```

## ۴. نمونه پاسخ درخواست توکن

```
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Pragma: no-cache
Content-Type: application/json; charset=utf-8
```

```
X-IPG-Url: https://neo-pg.sep.ir/transaction/init
```

```
Date: Sun, 07 Jan 2024 05:22:20 GMT
Content-Length: 55
```

```
{"status": 1, "token": "496a7e405c47406dab0d8b5e3d9c85ec"}
```